




Setting Up Your Email in Windows (Vista) Mail


You can set up Windows (Vista) Mail to work with your email account.

To Set Up Your Email Account in Windows (Vista) Mail

1. In Microsoft Mail, from the **Tools** menu, select **Accounts**.



2. In the **Internet Accounts** window, click **Add** to add a new mail account.





Knight Tymes Designs, LLC

6120 W Encanto Blvd Phoenix Arizona 85035

623-931-7286 Fax 623-321-1930

www.ktdhosting.com/support

3. On the **Your Name** page, in the **Display Name** field, enter your full name and then click **Next**.

Your Name

When you send e-mail, your name will appear in the From field of the outgoing message. Type your name as you would like it to appear.

Display name:

For example: John Smith

[Where can I find my e-mail account information?](#)

Next Cancel

4. On the **Internet Email Address** page, in the **Email address** field, enter your email address and then click **Next**.

Internet E-mail Address

Your e-mail address is the address other people use to send e-mail messages to you.

E-mail address:

For example: someone@microsoft.com

[Where can I find my e-mail account information?](#)

Next Cancel



5. On the **Set up Email Servers** page, enter your information as follows and then click **Next**.

Incoming email server type

Select **POP3** from the drop down list.

Incoming mail (POP3 or IMAP) server

Type **mail.yourdomainname.com**

(replace *mail.yourdomain.com* with Your domain e.g. if your domain is *bobsite.com* then it should be *mail.bobsite.com*)

Outgoing email server (SMTP) name

Type **mail.yourdomainname.com** and select **Outgoing server requires authentication**.

(replace *mail.yourdomain.com* with Your domain e.g. if your domain is *bobsite.com* then it should be *mail.bobsite.com*)

Set up e-mail servers

Incoming e-mail server type:
POP3

Incoming mail (POP3 or IMAP) server:
pop.secureserver.net

Outgoing e-mail server (SMTP) name:
smtpout.secureserver.net

Outgoing server requires authentication

[Where can I find my e-mail server information?](#)

Next Cancel

6. On the **Internet Mail Logon** page, in the **Email Username** and **Password** fields, enter your email address and password for your email account, and then click **Next**.

Internet Mail Logon

Type the account name and password your Internet service provider has given you.

E-mail username: janesmith@coolexample.com


Password:

Remember password


Next Cancel



7. Click Finish.




8. Return to Microsoft Mail, and from the **Tools** menu, select **Accounts**.





9. In the **Internet Accounts** window, under your list of Mail accounts, select the account you just set up and then click **Properties**.



10. In the **Properties** window, go to the **Advanced** tab.

11. Under **Server Port Numbers**, in the **Outgoing mail (SMTP)** field, type **28** and then click **OK**.





Knight Tymes Designs, LLC

6120 W Encanto Blvd Phoenix Arizona 85035

623-931-7286 Fax 623-321-1930

www.ktdhosting.com/support
